

Expand a Hard Disk with Ubuntu LVM

- [Expand a Hard Disk with Ubuntu LVM](#)

Expand a Hard Disk with Ubuntu LVM

So you're running an Ubuntu server in a virtual machine, and now you need to add 20 GB of disk space to root (/). There are quite a few ways to do this, and fortunately you're running the [Logical Volume Manager\(link is external\)](#) (LVM) in Ubuntu, so the process isn't too bad.

(This example uses Ubuntu Server 12.04, but it works for 14.04, 16.04 and 18.04 as well.)

After you make the additional space available in VMWare/Xen/Hyper-V, first reboot your Ubuntu server so it can see the new free space. Then we'll run the GNU partition editor to examine our disk:

```
root@myserver:/# parted
GNU Parted 2.2
Using /dev/sda
Welcome to GNU Parted! Type 'help' to view a list of commands.
(parted) print free
Model: VMware Virtual disk (scsi)
Disk /dev/sda: 42.5GB
Sector size (logical/physical): 512B/512B
Partition Table: msdos
```

Number	Start	End	Size	Type	File system	Flags
	32.3kB	32.8kB	512B		Free Space	
1	32.8kB	255MB	255MB	primary	ext2	boot
	255MB	255MB	8192B		Free Space	
2	255MB	16.1GB	15.8GB	extended		
5	255MB	16.1GB	15.8GB	logical		lvm
3	16.1GB	21.5GB	5365MB	primary		
	21.5GB	21.5GB	6856kB		Free Space	
	21.5GB	42.5GB	21.0GB		Free Space	<-----

You can see your free space, so let's partition it:

```
$ cfdisk
```

Pick your free space, select New, then choose a Primary or Logical partition. For a small server, it probably doesn't matter too much.

Remember in x86 Linux that you can have a maximum of 4 primary + extended partitions per disk.

Beyond that, you'll need to begin adding logical partitions in your extended partitions.

Use partition type Linux LVM (8e).

Select the Write command to create the partition, then (if necessary) reboot your system.

When your system comes back up, check on your new partition:

```
$ fdisk -l /dev/sda
```

```
Disk /dev/sda: 42.5 GB, 21474836480 bytes
255 heads, 63 sectors/track, 2610 cylinders
Units = cylinders of 16065 * 512 = 8225280 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk identifier: 0x000d90ee
```

Device	Boot	Start	End	Blocks	Id	System
/dev/sda1	*	1	31	248832	83	Linux
Partition 1 does not end on cylinder boundary.						
/dev/sda2		31	1958	15476768	5	Extended
/dev/sda3		1958	2610	5239185	83	Linux
/dev/sda4		2610	3608	16815191	83	Linux <-----
/dev/sda5		31	1958	15476736	8e	Linux LVM

So now let's pull it into our LVM configuration. First we'll create the physical volume:

```
$ pvcreate /dev/sda4
Physical volume "/dev/sda4" successfully created
```

Let's take a look at our physical volumes:

```
$ pvdisplay

--- Physical volume ---
PV Name                /dev/sda5
VG Name                ubuntu-1004
```

```
PV Size          14.76 GiB / not usable 2.00 MiB
Allocatable      yes (but full)
PE Size          4.00 MiB
Total PE         3778
Free PE          0
Allocated PE     3778
PV UUID          f3tYaB-YCoK-ZeRq-LfDX-spqd-ggeV-gdsemo
```

--- Physical volume ---

```
PV Name          /dev/sda3
VG Name          ubuntu-1004
PV Size          5.00 GiB / not usable 401.00 KiB
Allocatable      yes
PE Size          4.00 MiB
Total PE         1279
Free PE          11
Allocated PE     1268
PV UUID          rL0QG1-0muS-d4qL-d9u3-K7Hk-4a1l-NP3DtQ
```

"/dev/sda4" is a new physical volume of "20.00 GiB"

--- NEW Physical volume ---

```
PV Name          /dev/sda4
VG Name
PV Size          20.00 GiB
Allocatable      NO
PE Size          0
Total PE         0
Free PE          0
Allocated PE     0
PV UUID          uaJn0v-HbRz-YKv4-Ez83-jVUo-dfyH-Ky2oHV
```

Now, extend our volume group (ubuntu-1004) into our new physical volume (/dev/sda4):

```
$ vgextend ubuntu-1004 /dev/sda4
Volume group "ubuntu-1004" successfully extended
```

The whole purpose of this exercise is to expand the root filesystem, so let's find our main logical volume:

```
$ lvdisplay
```

```
--- Logical volume ---
LV Name                /dev/ubuntu-1004/root
VG Name                ubuntu-1004
LV UUID                UJQUwV-f3rI-Tsd3-dQY0-exIk-LSpq-2q1s13
LV Write Access        read/write
LV Status               available
# open                  1
LV Size                 19.39 GiB
Current LE              1892
Segments                1
Allocation              inherit
Read ahead sectors     auto
- currently set to     256
Block device           254:0
```

Now, let's extend the logical volume to all free space available:

```
$ lvextend -l+100%FREE /dev/ubuntu-1004/root
```

Next, extend the filesystem:

```
$ resize2fs /dev/mapper/ubuntu--1004-root
```

Finally, let's check our free space:

```
$ df -h
Filesystem                Size  Used Avail Use% Mounted on
/dev/mapper/ubuntu--1004-root
                          39G   14G   24G   37% / <----
none                       495M  176K  495M   1% /dev
none                       500M    0  500M   0% /dev/shm
none                       500M   36K  500M   1% /var/run
none                       500M    0  500M   0% /var/lock
none                       500M    0  500M   0% /lib/init/rw
/dev/sda1                  228M  144M   72M  67% /boot
```