Update vtenext from 18ce to 19ce

General premises

> The update is valid only for **vtenext 18ce**

> **You have to enable cron in order to run the update**


> **Please backup the files and the database of vtenext before the update. Follow the instructions in this link.**

Update


- Open this link and download `18ce_UpdateModule.zip` and `18ce_updater.zip`

Name	Modified	Size
Parent folder		
18ce_UpdateModule.zip	< 4 hours ago	44.4 kB
18ce_updater.zip	< 4 hours ago	451 Bytes


- Extract the content of `18ce_updater.zip`





- Copy `18ce_updater` with its contents inside the root folder of vtenext
- Open your web browser and navigate to the url where you installed vtenext. Login and then navigate to updater.html (eg. localhost:81/updater.html) and the page will redirect to the application settings



- Upload `18ce_UpdateModule.zip` file



Caricamento file
This PC › Documents ›
Search Documents
Organize
New folder
This PC
3D Objects
Desktop
Documents
Downloads
Music
Pictures
Videos
Local Disk (C:)
DVD Drive (D:) C
public (\\junior)
Network
Name
Date modified
Type
18ce_updater
11/19/2019 5:39 PM
18ce_UpdateModule
11/19/2019 5:38 PM
File name:
18ce_UpdateModule
Tutti i file
Open
Cancel
CANCEL


Settings > Module settings > Upgrade
Manage Module behaviour inside VTENEXTCE
Select the Package File
* File location:
Sfoglia...
18ce_UpdateModule.zip
VTENEXTCE Module is packaged as a zip file.
UPGRADE
CANCEL



Settings > Module settings > Upgrade
Manage Module behaviour inside VTENEXTCE
Verify Upgrade Details
Module Name
Update
Module Directory
modules/Update
Version
1.1 [Installed Version 1.0]
Req. VTENEXTCE version
18.05
Do you want to proceed with the upgrade?
YES
NO

If you have cron enabled, wait 12 hours (the updater checks every 12 hours to avoid server overloads). Otherwise, enable it.

- After 12 hours you will receive a new notification with this text "An update of vtenext is available. Click here for details"




- Click the notification and a new page will open with the details of the update



- Click "Schedule Update" and now there will be 2 scenarios depending on the operating system you are using


Windows

> **Automatic update is not supported on Windows.**





Follow the on-screen instructions to update.


- Backup files and database
- Download the update package
- Unzip the downloaded file and overwrite with its contents the root folder of vtenext



- Follow the point 4 of the instructions


Settings - VTENEXTCE 18.05
Update - VTENEXTCE 18.05
localhost:8019/index.php?module=U
Settings > Update
Update Version
Current build
1711
Update to
1817
UPDATE
U



Settings - VTENEXTCE 18.05
Update - VTENEXTCE 18.05
localhost:8019/index.php
Updating, please wait...
M




Done!

Linux

Enter the date and the time in which you want to schedule the update and the list of users to alert.



Wait until the selected time and after a while you will see the vtenext in maintenance mode.



Once the maintenance screen disappears, logout and login from vtenext.

Done!

Revision #36
Created 2019-11-25 10:21:39 UTC by manuel.tagliapietra
Updated 2019-11-26 13:30:54 UTC by manuel.tagliapietra