


15 Other Functions

- [15.1 RSS](#)
- [15.2 My Sites](#)
- [15.3 License and number of users](#)
- [15.4 Synchronizations](#)

15.1 RSS


It is possible to provide constant and real time updates to all vtenext users through the RSS Feed links available on the web or specially created by the company. vtenext provides the option of choosing from a list of RSS feeds available for users and viewing every available article on the display.

Each RSS feed has a unique address similar to the web URL searched for on the Internet. To see an RSS feed, you must enter this address in vtenext.



15.2 My Sites

This area allows you to view websites of interest directly on vtenext. The system is also very useful for connecting to shipment tracking or communicating with web-based suppliers.




15.3 License and number of users

The Copyright and the License icon is found on the bottom right-hand corner of all vtenext pages; by clicking on it, you can access a popup containing all the terms of use of the program's Business license.

Since the 19.10 version, and only for **On-Site installations**, you can see how many users are available for that particular license and how many of them have been activated.

The **expiration date** of the installed license is also available in the same popup.



License on Cloud

✖

Licenza numero:

Utenti attivi: 5 di 9

Data di scadenza: Venerdì 05-05-2023

[Aggiorna la tua licenza](#)

VTENEXT Business License

The VTENEXT software ("the Software") is copyright © 2017 VTENEXT SRL of VERONA, Italy ("VTENEXT"). Use of the Software is permitted subject to the below terms and conditions. A company or other legal entity wishing to deploy the Software ("Customer") must accept these terms. Without acceptance, Customer may not use the Software except as permitted under the GNU Affero General Public License version 3 ("AGPL").

Article 1. Grant of license

VTENEXT hereby grants Customer a limited, non-exclusive license to install, deploy and use the Software for its business operations.

The license is limited to Customer. Customer may not distribute copies to third parties, and may not make available functionality of the Software to third parties, for example through a Software-as-a-Service business models or by offering the services of the Software to third parties. Independent contractors working for the sole benefit of Customer, e.g. consultants and temporary employees hired through a staffing agency, are not considered third parties. The license includes the right to make modifications to the Software and to have independent contractors make modifications to the Software for the sole benefit of Customer.

VTENEXT may make available optional modules to the Software for separate use. If and when Customer acquires such modules, the present license terms shall apply to such modules. All references to the Software shall be construed as applying to modules, except where indicated otherwise.

The Software is licensed, not sold. No copyrights or other intellectual property rights are transferred to Customer. The intellectual property on any modifications made by or for Customer shall rest with Customer, subject to the underlying intellectual property rights of VTENEXT.


License On-Site

15.4 Synchronizations

From vtenext settings the crm synchronization function can be accessed with other applications. The synchronizable platforms available are as follows:

- Hubspot
- Salesforce
- SuiteCRM
- Jira
- vtiger
- Magento
- Prestashop
- Shopify
- WooCommerce

The synchronizable modules are different and based on the chosen platform. The following diagram summarizes which modules can be synchronized.

Hubspot (only cloud version)	<ul style="list-style-type: none">• Trouble Ticket• Accounts• Contacts• Potentials• Targets• Users <p>*record deletions from Hubspot to vtenext are not covered</p> <p>N.B. The "scopes". The crm indicates to insert the following "scopes":</p>  <p>ATTENTION: it is essential to select exactly those indicated, otherwise the synchronization will not work!</p>
-------------------------------------	---

Salesforce	<ul style="list-style-type: none"> • Trouble Ticket • Ticket Comments • Ticket Attachments • Emails • Accounts • Campaigns • Contacts • Installations • Leads • Potentials • Products* • Users
SuiteCRM (only on-premise version)	<ul style="list-style-type: none"> • Trouble Ticket • Accounts • Campaigns • Contacts • Installations • Leads • Potentials • Products* • Users <p>*images are not imported</p>
Jira (only cloud version)	<ul style="list-style-type: none"> • Trouble Ticket • Project Tasks • Projects • Ticket Comments • Users
vtiger (only cloud version)	<ul style="list-style-type: none"> • Trouble Ticket • Accounts • Contacts • Vendors • Installations • Leads • Potentials • Products* • Services • Users <p>*images are not imported</p>
Magento (only on-premise version 2.4.0)	<ul style="list-style-type: none"> • Accounts • Currencies • Sales Orders • Products* • Configurable products • Taxes <p>*images are not imported</p>

Prestashop (only on-premise version 1.7.6.7)	<ul style="list-style-type: none"> • Accounts • Currencies • Sales Orders • Products* • Configurable products • Taxes <p>*images are not imported</p>
Shopify (only cloud version 2019-20)	<ul style="list-style-type: none"> • Accounts • Currencies • Sales Orders • Products* • Configurable products <p>*images are not imported</p>
WooCommerce (only on-premise version 4.4.0)	<ul style="list-style-type: none"> • Accounts • Currencies • Sales Orders • Products* • Configurable products • Taxes <p>*images are not imported</p>
Zendesk	<ul style="list-style-type: none"> • Trouble Ticket • Accounts • Ticket Comments • Ticket Attachments • Users

When accessing the configuration page from **SETTINGS > BUSINESS PROCESS MANAGER > SYNCHRONIZATIONS** the synchronization to be set and towards which system can be configured with a few simple steps. The page is identical to the page shown in the image below.

Settings > Synchronizations
Configure external systems for data synchronization

Create synchronization Save Cancel

General settings

External system Vtiger The external system to connect to

Instance URL https://your_instance.odx.vtiger.com

Modules to synchronize	Available modules	Selected modules
	Accounts	
	Assets	
	Contacts	
	Leads	
	Potentials	
	Products	
	Services	
	Trouble Tickets	
	Users	
	Vendors	

Authentication

Type Basic HTTP Authentication method to use


Username username It should be an administrative user

Password

VTENEXT 22.05 © 2008-2022 Vtenext.com | License


Configuration

1. The first required action is to choose the **External system** in the available drop-down menu
2. Specify the **Instance address** to which you wish to connect (where required)
3. Now choose the required synchronization modules from those available and take them to the **Selected modules** column by means of the right-pointing arrow
4. Once the operation in step 3 has been completed, a popup will open in which you can select the synchronization method for each of the selected modules (see example in the image below)



View of the synchronization configuration of the Trouble Ticket module selected in point 3

5. Enter the authentication data, stating the authentication mechanism **Type**, **Username** and **Password** for login. By clicking on the  icon it is possible to have further information to retrieve the data to be entered in the username and password that differ for each synchronizable platform.



N.B.: synchronization occurs in accordance with the interval set for the crons, which is every minute by default, but which can be subject to variation depending on the number of synchronizations set, other cron processes, and the machine workload.