

# 6.3 SMS Module

vtenext can be enabled to send SMS text messages. To configure the transmission of SMS messages, login in as an Admin user and go to Settings > Outbound SMS server.

To enable the transmission of SMS messages from vtenext you need to set up an email-to-sms service. This service can be requested from your mobile communications provider or by contacting vtenext partners. Once the service has been set up you can define the email addresses authorised to use the service.

In general, to send an SMS from the email function simply send an email to a recipient address with the following structure:

country code and callee number @ service provider domain.it/ com/...

To use the service directly from the recipient record (lead or contact), click SEND SMS in the green OTHER tab: the system automatically composes the recipient's email address without the user being aware or being able to view this operation.

In summary, to set an SMS message you must specify the following information in vtenext:

- data of the mailbox enabled to send SMS messages;
- country code;
- SMS service provider domain.

<b>Server Name</b>	Specify the outbound email server address referred to the mailbox enabled for sending SMS messages
<b>User Name</b>	Login to access the mailbox
<b>Password</b>	Password associated with the mailbox
<b>Requires Authentication?</b>	Specify Yes/No depending on the characteristics of the email server (generally Yes)
<b>Domain to apply to SMS numbers</b>	This info is supplied by the SMS service provider

<b>SMS service account</b>	State the account name for the SMS service; this information is supplied by the SMS service provider
<b>Code to apply to SMS numbers</b>	Specify the country code (39 for Italy)
<b>Name displayed in the SMS message</b>	This function depends on the service provider - it might not be enabled

Settings > Outgoing Sms service  
Configure your Outgoing Sms Server

Sms Server Settings EDIT

Server Type

Server Name

User Name

Password

Requires Authentication? No

Domain to apply on sms numbers

Account for the sms service

Prefix for sms numbers

Name displayed on sent sms

Server name \* = It may be necessary to add the port (e.g. mail.miodominio.it:port) SMS service account \* = It may be necessary to use the email address entered in the Username field.

(es. box.enable@mydomain.com)

---

Revision #1

Created 2022-05-25 17:25:49 UTC by Alberto

Updated 2022-06-06 12:30:15 UTC by Alberto